


IN THE SOUTHERN PLAINS

May 10, 2012

Upcoming Meetings


- 2012 Texas Water Summit
 - May 20-21, Austin
 - Goal: bring together scientists, engineers, policy analysts, legislators, CEO's and agency officials to develop a common understanding of the science, technology, economics and policy requirements needed to address Texas' emerging water security challenges.
 - More Information:
 http://www.tamest.org/events/2012-water-summit.html
- South Central Climate Science Center Roll-out meetings:
 - Houston/Galveston, June 12
 - More being scheduled
 - More information: http://southcentralclimate.org





CoCoRaHS

- http://www.cocorahs.org/
- Daily rainfall, hail & snowfall measurements from more than 12,000 volunteers across the country
- High-resolution, high-quality data for analysis of drought, floods, water supply, forecasting, education, mosquito control...
- All you need is a rain gauge!



Coming Soon: The Hydrologic Cycle: http://www.youtube.com/cocorahs/

Regional Drought Monitor Update

Brian Fuchs, Climatologist

National Drought Mitigation Center School of Natural Resources University of Nebraska-Lincoln




SCIPP/NIDIS Drought Webinar Series, March 22, 2012









The Drought Monitor focuses on broad-scale conditions. Local conditions may vary. See accompanying text summary for forecast statements.

(e.g. hydrology, ecology)

http://droughtmonitor.unl.edu/









Released Thursday, May 10, 2012 Author: Matthew Rosencrans, NOAA/NWS/NCEP/CPC

U.S. Drought Monitor


May 10, 2012

Valid 7 a.m. EST

South Central United States

Drought Conditions (Percent Area)

	None	D0 - D4	D1 - D4	D2 - D4	D3 - D4	D4
Current	39.71	60.29	48.49	34.42	15.33	3.72
Last Week (5/1/2012)	39.19	60.81	46.96	35.06	15.80	5.29 I
3 Months Ago (2/7/2012)	21.93	78.07	70.73	53.64	31.94	11.58
1 Year Ago (5/3/2011)	10.60	89.40	83.35	71.08	49.80	14.68



<u>Intensity:</u>





The Drought Monitor focuses on broad-scale conditions. Local conditions may vary. See accompanying text summary for forcast statements.

USDA











http://droughtmonitor.unl.edu

Released Thursday, May 8, 2012 Matthew Rosencrans, Climate Prediction Center/NCEP/NWS/NOAA













CPC 8-14-Day Outlooks











What's new.....





VIC Soil Moisture Percentiles (wrt/ 1916-2004) 20120507




GRACE Data Assimilation

- Scientists at NASA's Goddard Space Flight Center generate groundwater and soil moisture drought indicators each week. They are based on terrestrial water storage observations derived from GRACE satellite data and integrated with other observations, using a sophisticated numerical model of land surface water and energy processes.
- These products are found at the National Drought Mitigation Center's webpage: http://drought.unl.edu/ MonitoringTools/NASAGRACEDataAssimilation.aspx







University of Washington Products using the VIC model

http://www.hydro.washington.edu/forecast/monitor/index.shtml

Disclaimer

Experimental Surface Water Monitor for the Continental U.S.



Current Condition

VIC Plots
MULTI-MODEL Plots
Drought Indices
MULTI-MODEL Drought
Severity
Data

Forecasts

VIC ESP Plots

(1915-present

SM & SWE Plots

Note: Popup blocking
prevents Archive access



Current percentiles for soil moisture, SWE and other variables with respect to the climatological period (1916-2004 for CONUS and 1926-2004 for Mexico). These update daily by 11-12 pm PST, and have a lag of 1-2 days. Roll the mouse over links below (or click) to see different maps. Note: SM & SWE maps are for daily values, whereas RO maps are for cumulative values.

SW Monitor description: (Wood, 2008)

	Soil Moisture	SWE	Total Moisture Storage (SM+SWE)	Cumulative Runoff
Current Plots	~CPC [cmpr] ~DM [cmpr]	curr	curr	1mo 2mo 3mo 6mo 9mo 12mo 18mo 24mo 36mo 48mo 60mo WY
Recent Changes	<u>1 wk 2 wk 1 mo</u>	<u>1 wk 2 wk 1 mo</u>	-	

Regional Maps


SM: West Central East Washington State

Useful Links

- -- <u>DM/7-Day</u> Streamflow mashup -- <u>DM Unified Blend /</u>
- VIC Soil Moisture Percentiles (wrt/ 1916-2004)
 20120507
 -120' -112' -104' -96' -88' -80' -72'


 48'
 44'
 40'
 36'
 32'
 28'
 24'
 20'
 16'
 0 2 5 10 20 30 70 80 90 95 98 100


percentile



North American Land Data Assimilation System (NLDAS)

http://www.emc.ncep.noaa.gov/mmb/nldas/drought/





Contact Information:

Brian Fuchs
bfuchs2@unl.edu
402-472-6775
National Drought Mitigation Center
School of Natural Resources
University of Nebraska-Lincoln









Ground Water/Surface WaterInteractions

Robert Puls, Ph.D.
Director, Oklahoma Water Survey



Oklahoma's Challenge

Increasing demands for sources of water, combined with changing land use, population growth, aging infrastructure, and climate change, pose significant threats to our state's water resources.

Failure to manage our state's waters in an integrated, sustainable manner will limit economic prosperity and jeopardize both human and aquatic ecosystem health.



The University of Oklahoma

Ground Water and Surface Water

Ground Water: Is often taken for granted because of "out of sight-out of mind mentality".

Understanding the connections between ground and surface water as part of the hydrologic cycle is crucial to successfully managing water resources.




Ground Water/Surface Water Interactions (GSI)

It's ALL connected - exchange of water in and out of the stream bed and banks


Gaining stream: Stream that is being recharged by adjacent ground water

Losing stream: Stream that is recharging the ground water



The University of Oklahoma

Losing Stream




Ground Water/Surface Water Interactions (GSI)

Temperature of stream sediment a good measure for mapping gaining and losing reaches of streams

Gaining stream: Sediment temperature fairly constant


Losing stream: Sediment temperature varies widely and tracks water column temperature.






The University of Oklahoma

- Disconnected streams: Losing streams where no connection exists between stream and ground water
- Bank storage: rapid rise in stream stage that causes water to move from the stream into the streambanks; usually is caused by storm precipitation, rapid snowmelt, or release of water from a reservoir



GSI occurs at several temporal or spatial scales:


- Watershed scale GSI is on the order of miles and involves ground water discharge over an entire watershed which supplies the stream base flow.
- Near-stream scale GSI, on the order of feet and days, captures the losing/gaining reaches of streams that support aquatic and riparian habitats.



GSI greatly influenced by the presence of vegetation along streams, rivers, lakes:


 Buffer strips and riparian zones act to improve stream water quality through bank stabilization, reducing pollutant loading from overland flow and sediment loading

These vegetation zones also support terrestial and




 Sediment scale GSI refers to exchanges in the stream beds and banks that occur on the scale of inches and minutes.

GSI in the near-stream and sediment scale is often called hyporheic flow.



• The hyporheic zone is critical in support of aquatic life and important in terms of regulation of contaminant transport in subsurface systems.



 The extent of the hyporheic zone depends on the 3 dimensional character of the stream. This zone expands with meandering streams and varies with streambed slope changes as well.







Figure 14. Surface-water exchange with ground water in the hyporheic zone is associated with abrupt changes in streambed slope (A) and with stream meanders (B).


- The hyporheic zone is characterized by variations in oxygen levels, microbial processes and the speciation of inorganic compounds (e.g. N, Fe)
- This zone is an important source of nutrient uptake via microbial processes, and adsorption, precipitation reactions controlling inorganic-organic transport



GSI and Pumping Wells

Wells can draw divert water discharging to adjoining streams and increased pumping can draw all water away from


streams resulting in reduced flows and Negative impacts to aquatic Organisms.





Thank You for Your Attention

Acknowledgements: Graphics from USGS Circular 1139



Groundwater Recharge and Drought



Larry French, P.G.

Director, Groundwater Resources
Texas Water Development Board
May 10, 2012





Outline

- Recharge: what is it? how is it measured?
- Recharge conditions: a tale of two aquifers
- Groundwater management and drought: know your aquifer





- Recharge: what is it? how is it measured?
- Recharge conditions: a tale of two aquifers
- Groundwater management and drought: know your aquifer





recharge



vadose zone

recharge

water table

Recharge is water that infiltrates to the water table of an aquifer.

aquifer

aquitard/confining layer





how is recharge measured?

- Estimated is a better term than "measured."
- Diffuse or focused
- See next slide for:
 - Surface water
 - Unsaturated Zone
 - Saturated Zone



Table 2. Suggested techniques for quantifying recharge to the major aquifers in Texas; E, Edwards aquifer; E-T, Edwards Trinity aquifer; CPA, Cenozoic Pecos Alluvium aquifer; GC, Gulf Coast aquifer; HMB, Hueco Mesilla Bolson; O, Ogallala aquifer; S, Seymour aquifer; and T, Trinity aquifer.

	Е	E-T	CW	CPA	GC	HMB	0	S	Т
Surface Water									
Channel water budget	√		√				√		
Baseflow discharge		✓	✓						✓
Seepage meters							√		
Heat tracers						√	✓		
Watershed modeling	√				√				√
Unsaturated Zone									
Zero Flux Plane	✓	√	✓	√	√				
Tracers									
C1			✓	√	✓		√		√
36C1/C1			✓	√	✓	√	✓		✓
3H			✓	√	√	~	✓	✓	√
Modeling			√	√	✓	√	√	√	√
Saturated Zone									
Water table fluctuations			✓		✓			√	√
Tracers									
C1			✓		✓	✓			✓
<i>3</i> H		√	√	√	√	~	✓	√	√
<i>3</i> H/ <i>3</i> He			✓	√	√	~	✓	✓	✓
CFCs		✓	✓		✓		✓		✓
14C			✓			~			√
Modeling	√		√	√	✓	√	✓	√	√

Source:

"Groundwater Recharge in Texas" by Bridget Scanlon, Alan Dutton, Marios Sophocleous





- Recharge: what is it? how is it measured?
- Recharge conditions: a tale of two aquifers
- Groundwater management and drought: know your aquifer






Recharge varies considerably


- High Plains/Ogallala aquifer: 0.004 to 1.7 in/ yr (outside irrigated areas) and 0.5 to 8.6 in/ yr (playa-focused)
- Edwards aquifer: dynamic, highly variable






Water retained as a film on rock surfaces and in capillary—size openings after gravity drainage.

Heath, 1987












McDonald Irrigation Well, 1200 Gallons per Minute, Hereford, Texas.






Water level changes High Plains Aquifer


Scientific Investigations
Report 2011-5089
USGS






Graphic from Playa Lakes Joint Venture







cross-section - structure



Development Board







July 2011 Groundwater Levels in Edwards Aquifer observation wells

- Declined in thirteen monitoring wells
- The J-17 well in San Antonio recorded a water level of 88.88 feet below land surface. This water level is 7.88 feet below the Stage II critical management level in that segment of the Edwards Aquifer. Stage II restrictions were triggered on June 1, 2011 by the Edwards Aquifer Authority after the 10 day average of water levels fell below 650 foot elevation or 81 feet below land surface.



(8) State Well ID 68-37-203 (J-17) In San Antonio, Bexar County Edwards (BFZ) Aquifer





The late April water level measurement in this Edwards (BFZ) Aquifer well, elevation 731 feet above sea level, was 84.08 feet below land surface. This was 19.09 feet below last month's measurement, 6.92 feet below last year's measurement, and 37.44 feet below the initial measurement recorded in 1932.

*** Water levels below the red line indicate Edwards Aquifer Authority Stage I drought restrictions. ***






- Recharge: what is it? how is it measured?
- Recharge conditions: a tale of two aquifers
- Groundwater management and drought: know your aquifer




Public Water Supply Systems Affected by Drought



Spicewood Beach, near Austin

- Groundwater supply from shallow wells screened in Colorado River alluvium (normally inundated by Lake Travis).
- Lake Travis water level declined significantly in drought of 2011.
- By early 2012, groundwater levels in alluvium had also decreased to the point that the water supply wells were dry.

Spicewood Beach Area Wells





Declining groundwater levels can affect surface water resources

TWDB has evaluated several factors that have played a role in the decline in Lake Meredith storage. Reductions in:

- Releases from Ute Dam (upstream in New Mexico) ~ 32%
- Irrigation from return flows from Revuelto Creek (downstream of Ute Dam) - ~23%
- Base flow due to declining groundwater levels ~ 22%
- Runoff from precipitation ~ 18%
- Other factors ~5%

These are estimates based on comparison of conditions for 1965-2000 and 2001-2006.



Contact Information



Larry French, P.G.

Director, Groundwater Resources
Texas Water Development Board

larry.french@twdb.texas.gov

512-463-5067

www.twdb.texas.gov





ABRFC Experimental Soil Moisture Graphics

Eric Jones/Lee Crowley
Arkansas/Red River Forecast Center
National Weather Service
Tulsa, OK, USA



Soil Moisture Computation



- Uses the SACSMA continuous soil moisture operation of the 4x4 km OHD distributed hydrologic model
- 17 model parameters
- Model parameters based on soil type/land use.
- Climatological PE used



Soil Moisture Computation (continued)



- Uses hourly QPE rainfall from radar/gage computations
- Model run in a hourly time step.
- Upper layer computed from upper zone tension and free water values
- Lower layer from lower zone tension, primary and supplementary values.



Soil Moisture Computation (continued)



- Hopefully more useful than total soil moisture as it is broken up into upper/ lower soil moisture.
- Upper zones more useful for agricultural use
- Lower zone useful for hydrologic/ground water use



Soil Moisture Graphic Computation




- Climate monthly statistics uses 16 years of model data from 1996-2011.
- Graphics produced daily around noon.
- Produced via the NWS Community Hydrologic Prediction System (CHPS)



Main page







Upper Zone Anomaly




- Sensitive to short term rainfall.
- Can change drastically from day to day, especially during large rainfall events.
- Representative of the first few inches of soil.



Upper Zone Anomaly







Lower Zone Anomaly




- Changes very slowly over time.
- Not extremely sensitive to rainfall events.
- Takes multiple rainfall events to drastically change values.
- Extends several feet down the soil column.



Lower Zone Anomaly







Anomaly notes



- Anomaly values more sensitive across climatologically dry areas.
- Any inputs on scale?



Upper Zone Moisture Values




- Percent fullness of 2 upper zone model parameter contents versus parameter maximums.
- Input needed on scale of legend/ categorical values



Upper Zone Moisture Values







Lower Zone Moisture Values




- Percent fullness of 3 lower zone model parameter contents versus parameter maximums.
- Input needed on scale of legend/ categorical values



Lower Zone Moisture Values








Webpage










QUESTIONS?



Arbuckle Simpson Aquifer Daune Smith, Choctaw & Chickasaw Nations



Major Groundwater Aquifers of Oklahoma Ogallala Salt Fork of the Arkansas River Arkansas River Ogallala Roubidoux Cimarron River Vamoosa-Major Alluvium and Terrace Aquifers Arkansas River —Garber-Wellington Major Bedrock Aquifers Ogallala_ North Canadian River_ Rush Springs Washita River North Fork of the Red River Canadian River Arbuckle-imbered Hills Red River **ARBUCKLE-SIMPSON AQUIFER**

100




The Arbuckle Simpson Aquifer is the only Sole Source aquifer in Oklahoma

(the aquifer supplies at least 50% of the drinking water in the area and users have no feasible alternative source)





Arbuckle Simpson Aquifer and Surrounding Communities



Arbuckle Simpson Groundwater Uses

OWRB study: approx. 25,000-30,000 AFY sustainably available Primary use is municipal, as appropriate for a sole source aquifer—approx. 5,000 AFY





Water is Important in this Region for Recreation & Tourism


Blue River state wildlife management area, Chickasaw National Recreation Area, Tishomingo NWR, Fish Hatchery, Turner Falls, The Nature Conservancy's Pontotoc Ridge Preserve and others—the hunting, fishing, hiking, wildlife observation, inn and hospitality services collectively draw millions of visitors each year, making a substantial contribution to the local economy.








Not All Aquifers are the Same





The unique features of the Arbuckle Simpson Aquifer (ASA) make it less absorbent and more fragile than more typical "alluvial" aquifers that are less rocky.

Very different effects of removing 1.0 ft surface water from aquifer.




Aguifer Hydraulic Properties:
Storage Coefficient
Alluvial aquifer 0.2
Arbuckle-Simpson aquifer 0.008


1 CUBIC
FOOT


Alluvial aquifer 1.5 gallons


The ASA absorbs far less rainwater than an alluvial aquifer.




Typical Cross-section of Karst Topography










Water levels in the aquifer were at historic low levels during the drought of 2011, but have rebounded to near normal levels with recent rains.

A low water level in the aquifer means less flow at the springs and therefore, less base flow in the streams.

Approved	Provisional	Historical	Range of	Historical Daily
Daily Data	Daily Data	Daily Median		Min & Max

Discharge on the Blue River at Blue during 1956



During the worst drought on record in 1956, the Blue River at Blue had 28 consecutive days with no recorded flow.

Discharge on the Blue River at Blue during 2011

The flow rate on the Blue River at Blue dropped below 1 cfs for 25 days during the worst portion of the 2011 drought.



Chickasaw National Recreation Area

The Chickasaw National Recreation Area (CNRA) posted signs warning people to stay out of stagnant water pools when the spring-fed creeks in the park stopped flowing during the 2011 drought.



Resources

- U.S. Drought Portal
 - http://www.drought.gov
- Southern Plains Information & Past Webinars
 - http://www.drought.gov/portal/server.pt/community/southern_plains
- Drought Impact Reporter
 - http://droughtreporter.unl.edu/
- State Climatologists
 - http://www.stateclimate.org/
- National Drought Mitigation Center
 - http://drought.unl.edu/
- Southern Climate Impacts Planning Program (SCIPP)
 - http://www.southernclimate.org/
 - Youtube: http://www.youtube.com/user/SCIPP01
- Climate Assessment for the Southwest (CLIMAS)
 - http://www.climas.arizona.edu/



We are now on facebook!
Southern Climate Impacts Planning Program

Is drought properly classified in your region? If not, let us know!

- Drought Impact Reporter
- Contact your State Climatologist
- •E-mail the DM Authors: droughtmonitor@unl.edu